

Dovecot — Error: net_connect_unix(/var/run/dovecot/stats-writer) failed: Permission denied

После обновления Dovecot в логах postfix-а maillog начала проскакивать ошибка вида:

```
Error: net_connect_unix(/var/run/dovecot/stats-writer)
failed: Permission denied
```

Читаем на сайте:

<https://wiki2.dovecot.org/Upgrading/2.3>

```
service stats {
    unix_listener stats-writer {
        user = vmail
        #mode = 0666 # Use only if nothing else works. It's a bit
insecure, since it allows any user in the system to mess up
with the statistics.
    }
}
```

где vmail — пользователь под которым работает Dovecot, у меня это nobody. Дописываем в конец файла и рестартуем сервис:

```
# ee /usr/local/etc/dovecot/conf.d/10-master.conf
```

```
## NEW
```

```
service stats {
    unix_listener stats-writer {
        user = nobody
        #mode = 0666 # Use only if nothing else works. It's a bit
insecure, since it allows any user in the system to mess up
with the statistics.
    }
}
```

##